
# RMC Filter Evaluation (Continuation) Toolbox

RMC Internal Erosion Suite

RMC-CPD-2023-04 January 2024



## Prepared By:

Adam Gohs, Risk Management Center

# Reviewed By:

Tim O'Leary, Risk Management Center

# Approved By:

Nate Snorteland, Risk Management Center

# Contents

1	Design for Particle Retention		4
	1.1	Base Soil Characterization	4
	1.2	Filter Material Characterization	4
	1.3	Particle Retention Criterion	4

import Figure from "@site/src/components/Figure"; import FigReference from "@site/src/compone import Citation from "@site/src/components/Citation"; import CitationFootnote from "@site/src/components/CitationFootnote"; import NavAndPrint from "@site/src/components/NavAndimport Link from "@docusaurus/Link"; import addBaseUrl from "@docusaurus/useBaseUrl";

# 1 Design for Particle Retention

Modern filter design criteria for particle retention are based on providing a no-erosion condition. The no erosion condition occurs when a filter material is sufficiently fine to seal with no erosion, or practically no erosion, of the base material. This worksheet assesses the particle retention criterion for no erosion and helps to screen potential failure modes if no erosion is expected. If a filter fails the no-erosion screening, the other erosion boundaries using the Foster and Fell method described in section 8 are evaluated to assess how much erosion is required for self-filtering to occur and whether it can be tolerated.

#### 1.1 Base Soil Characterization

Step 1 characterizes the base soil. The fines content (FC), or percent passing the No. 200 sieve size by weight, of the finest base soil after regrading (if applicable) is obtained from the Base Gradation worksheet, where it is interpolated using a logarithmic scale for particle size and linear scale for percent passing. The base soil category (BSC) is assigned based on the FC of the finest base soil after regrading (if applicable). Use the drop-down list to select whether the base soil is non-dispersive or dispersive. Loading... is an example of step 1.

## 1.2 Filter Material Characterization

Step 2 characterizes the filter material. The coarsest D15F is obtained from the Filter Gradation worksheet, where it is interpolated using a logarithmic scale for particle size and linear scale for percent passing. Loading... is an example of step 2.

## 1.3 Particle Retention Criterion

Foster and Fell and Sherard et al. show that the measurable property of the filter that best defines its particle retention capability is the D15 of the filter (D15F). Research also shows that the correlation between D15F and the d85 of the base soil being protected by the filter (D85B) provides the best correlation for successful particle retention.

Sherard and Dunnigan developed the No-Erosion Filter (NEF) test to find the ratio of D15F and D85B that establishes a no-erosion condition for non-dispersive base soils. Additional research by Foster and Fell at the University of New South Wales (UNSW) helped in developing the no erosion condition for dispersive base soils. The results of the NEF and UNSW tests were used to develop the modern filter design criteria for particle retention in FEMA .

Step 3 evaluates the no-erosion particle retention criterion by comparing the coarsest D15F to the maximum allowable D15F based on the BSC and knowing whether the base soil is non-dispersive or dispersive. The criteria are a function of D85B and FC, as shown in Loading... and Loading... If the coarsest D15F is less than or equal to the maximum allowable D15F, "Meets" displays next to the calculation. If the criterion is not

met, "Fails" displays next to the calculation. A green background displays if the particle retention criterion is met, and an orange background displays if the particle retention criterion is not met.

Based on the particle retention criterion, a statement appears after the calculations indicating if the filter material satisfies the no-erosion particle retention criterion or is too coarse to satisfy the no-erosion particle retention criterion. If the particle retention criterion for no erosion is not met, use the Foster and Fell method to further evaluate the effectiveness of the filter material for particle retention. Loading... and Loading... are examples of the two possible scenarios for the no-erosion particle retention criterion.